

## nag\_ode\_ivp\_rk\_onestep (d02pdc)

### 1. Purpose

**nag\_ode\_ivp\_rk\_onestep (d02pdc)** is a one-step function for solving the initial value problem for a first order system of ordinary differential equations using Runge-Kutta methods.

### 2. Specification

```
#include <nag.h>
#include <nagd02.h>

void nag_ode_ivp_rk_1step(Integer neq, void (*f)(Integer neq, double t, double y[],
                                               double yp[], Nag_User *comm),
                        double *tnow, double ynow[],
                        double ypnov[], Nag_ODE_RK *opt, Nag_User *comm,
                        NagError *fail)
```

### 3. Description

This function and its associated functions (**nag\_ode\_ivp\_rk\_setup (d02pvc)**, **nag\_ode\_ivp\_rk\_reset\_tend (d02pwc)**, **nag\_ode\_ivp\_rk\_interp (d02pxc)**, **nag\_ode\_ivp\_rk\_errass (d02pzc)**) solve the initial value problem for a first order system of ordinary differential equations. The functions, based on Runge-Kutta methods and derived from RKSUITE (Brankin *et al*, 1991), integrate

$$y' = f(t, y) \quad \text{given} \quad y(t_0) = y_0$$

where  $y$  is the vector of **neq** solution components and  $t$  is the independent variable.

This function is designed to be used in complicated tasks when solving systems of ordinary differential equations. You must first call **nag\_ode\_ivp\_rk\_setup (d02pvc)** to specify the problem and how it is to be solved. Thereafter you (repeatedly) call **nag\_ode\_ivp\_rk\_onestep** to take one integration step at a time from **tstart** in the direction of **tend** (as specified in **nag\_ode\_ivp\_rk\_setup (d02pvc)**). In this manner **nag\_ode\_ivp\_rk\_onestep** returns an approximation to the solution **ynow** and its derivative **ypnow** at successive points **tnow**. If **nag\_ode\_ivp\_rk\_onestep** encounters some difficulty in taking a step, the integration is not advanced and the routine returns with the same values of **tnow**, **ynow** and **ypnow** as returned on the previous successful step. **nag\_ode\_ivp\_rk\_onestep** tries to advance the integration as far as possible subject to passing the test on the local error and not going past **tend**. In the call to **nag\_ode\_ivp\_rk\_setup (d02pvc)** you can specify either the first step size for **nag\_ode\_ivp\_rk\_onestep** to attempt or that it compute automatically an appropriate value. Thereafter **nag\_ode\_ivp\_rk\_onestep** estimates an appropriate step size for its next step. This value and other details of the integration can be obtained after any call to **nag\_ode\_ivp\_rk\_onestep** by examining the contents of the structure **opt**, see Section 4. The local error is controlled at every step as specified in **nag\_ode\_ivp\_rk\_setup (d02pvc)**. If you wish to assess the true error, you must set **errass = Nag\_ErrorAssess\_on** in the call to **nag\_ode\_ivp\_rk\_setup (d02pvc)**. This assessment can be obtained after any call to **nag\_ode\_ivp\_rk\_onestep** by a call to the subroutine **nag\_ode\_ivp\_rk\_errass (d02pzc)**.

If you want answers at specific points there are two ways to proceed:

The more efficient way is to step past the point where a solution is desired, and then call **nag\_ode\_ivp\_rk\_interp (d02pxc)** to get an answer there. Within the span of the current step, you can get all the answers you want at very little cost by repeated calls to **nag\_ode\_ivp\_rk\_interp (d02pxc)**. This is very valuable when you want to find where something happens, e.g., where a particular solution component vanishes. You cannot proceed in this way with **method = Nag\_RK\_7.8**.

The other way to get an answer at a specific point is to set **tend** to this value and integrate to **tend**. **nag\_ode\_ivp\_rk\_onestep** will not step past **tend**, so when a step would carry it past, it will reduce the step size so as to produce an answer at **tend** exactly. After getting an answer there (**tnow = tend**), you can reset **tend** to the next point where you want an answer, and repeat. **tend** could be reset by a call to **nag\_ode\_ivp\_rk\_setup (d02pvc)**, but you should not do this. You should use

nag\_ode\_ivp\_rk\_reset\_tend (d02pvc) because it is both easier to use and much more efficient. This way of getting answers at specific points can be used with any of the available methods, but it is the only way with **method** = **Nag\_RK\_7\_8**. It can be inefficient. Should this be the case, the code will bring the matter to your attention.

#### 4. Parameters

##### neq

Input: the number of ordinary differential equations in the system to be solved.  
Constraint: **neq**  $\geq$  1.

##### f

This function must evaluate the first derivatives  $y'_i$  (that is the functions  $f_i$ ) for given values of the arguments  $t, y_i$ .

```
void f (Integer neq, double t, double y[], double yp[], Nag_User *comm)
```

**neq**  
Input: the number of differential equations.

**t**  
Input: the current value of the independent variable,  $t$ .

**y[neq]**  
Input: the current values of the dependent variables,  $y_i$  for  $i = 1, 2, \dots, \mathbf{neq}$ .

**yp[neq]**  
Output: the values of  $f_i$  for  $i = 1, 2, \dots, \mathbf{neq}$ .

**comm**  
Input/Output: pointer to a structure of type Nag\_User with the following member:

**p** - Pointer  
Input/Output: The pointer **comm**->**p** should be cast to the required type, e.g. **struct user \*s = (struct user \*)comm->p**, to obtain the original object's address with appropriate type. (See the argument **comm** below.)

##### tnow

Output: the value of the independent variable  $t$  at which a solution has been computed.

##### ynow[neq]

Output: an approximation to the solution at **tnow**. The local error of the step to **tnow** was no greater than permitted by the specified tolerances (see nag\_ode\_ivp\_rk\_setup (d02pvc)).

##### ypnow[neq]

Output: an approximation to the derivative of the solution at **tnow**.

##### opt

Input: pointer to a structure of type Nag\_ODE\_RK as initialised by the setup function nag\_ode\_ivp\_rk\_setup (d02pvc).

Output: the following structure members hold information as follows:

##### totfcn - Integer

The total number of evaluations of  $f$  used in the primary integration so far; this does not include evaluations of  $f$  for the secondary integration specified by a prior call to nag\_ode\_ivp\_rk\_setup (d02pvc) with **errass** = **Nag\_ErrorAssess\_on**.

##### stpcst - Integer

The cost in terms of number of evaluations of  $f$  of a typical step with the method being used for the integration. The method is specified by the parameter **method** in a prior call to nag\_ode\_ivp\_rk\_setup (d02pvc).

##### waste - double

The number of attempted steps that failed to meet the local error requirement divided by the total number of steps attempted so far in the integration. A "large" fraction indicates that

the integrator is having trouble with the problem being solved. This can happen when the problem is “stiff” and also when the solution has discontinuities in a low order derivative.

**stpsok** - Integer

The number of accepted steps.

**hnext** - double

The step size the integrator plans to use for the next step.

**comm**

Input/Output: pointer to a structure of type Nag\_User with the following member:

**p** - Pointer

Input/Output: The pointer **p**, of type Pointer, allows the user to communicate information to and from the user-defined function **f()**. An object of the required type should be declared by the user, e.g. a structure, and its address assigned to the pointer **p** by means of a cast to Pointer in the calling program, e.g. `comm.p = (Pointer)&s`. The type pointer will be `void *` with a C compiler that defines `void *` and `char *` otherwise.

**fail**

The NAG error parameter, see the Essential Introduction to the NAG C Library.

## 5. Error Indications and Warnings

**NE\_PREV\_CALL**

The previous call to a function had resulted in a severe error. You must call `nag_ode_ivp_rk_setup (d02pvc)` to start another problem.

**NE\_NO\_SETUP**

The setup function `nag_ode_ivp_rk_setup (d02pvc)` has not been called.

**NE\_RK\_INVALID\_CALL**

The function to be called as specified in the setup routine `nag_ode_ivp_rk_setup (d02pvc)` was `nag_ode_ivp_rk_range (d02pcc)`. However the actual call was made to `nag_ode_ivp_rk_onestep`. This is not permitted.

**NE\_PREV\_CALL\_INI**

The previous call to the function `nag_ode_ivp_rk_onestep` had resulted in a severe error. You must call `nag_ode_ivp_rk_setup (d02pvc)` to start another problem.

**NE\_NEQ**

The value of `neq` supplied is not the same as that given to the setup function `nag_ode_ivp_rk_setup (d02pvc)`. `neq = <value>` but the value given to `nag_ode_ivp_rk_setup (d02pvc)` was `<value>`.

**NE\_RK\_PDC\_TEND**

`tend (= <value>)` has been reached already. To integrate further with same problem the function `nag_ode_ivp_rk_reset_tend (d02pwc)` must be called with a new value of `tend`.

**NE\_RK\_PDC\_STEP**

In order to satisfy the error requirements `nag_ode_ivp_rk_onestep` would have to use a step size of `<value>` at current `t = <value>`. This is too small for the **machine precision**.

**NW\_RK\_TOO\_MANY**

Approximately `<value>` function evaluations have been used to compute the solution since the integration started or since this message was last printed.

**NE\_RK\_PDC\_GLOBAL\_ERROR\_T**

The global error assessment may not be reliable for `t` past `tnow`. `tnow = <value>`.

**NE\_RK\_PDC\_GLOBAL\_ERROR\_S**

The global error assessment algorithm failed at the start of the integration.

**NE\_RK\_PDC\_POINTS**

More than 100 output points have been obtained by integrating to **tend**. They have been sufficiently close to one another that the efficiency of the integration has been degraded. It would probably be (much) more efficient to obtain output by interpolating with `nag_ode_ivp_rk_interp` (d02pxc) (after changing to **method** = **Nag\_RK\_4.5** if you are using **method** = **Nag\_RK\_7.8**).

**NE\_STIFF\_PROBLEM**

The problem appears to be stiff.

**NE\_MEMORY\_FREED**

Internally allocated memory has been freed by a call to `nag_ode_ivp_rk_free` (d02ppc) without a subsequent call to the set up function `nag_ode_ivp_rk_setup` (d02pvc).

**6. Further Comments**

If `nag_ode_ivp_rk_onestep` returns with `fail.code` = **NE\_RK\_PDC\_STEP** and the accuracy specified by **tol** and **thres** is really required then you should consider whether there is a more fundamental difficulty. For example, the solution may contain a singularity. In such a region the solution components will usually be of a large magnitude. Successive output values of **ynow** should be monitored with the aim of trapping the solution before the singularity. In any case numerical integration cannot be continued through a singularity, and analytical treatment may be necessary.

If `nag_ode_ivp_rk_onestep` returns with a non-trivial value of `fail.code` (i.e., those not related to an invalid call) then performance statistics are available by examining the structure **opt** (see Section 4). Furthermore if **errass** was set to **Nag\_ErrorAssess\_on** then global error assessment is available by a call to the function `nag_ode_ivp_rk_errass` (d02pzc). The approximate extra number of evaluations of *f* used is given by  $2 \times \text{stpsok} \times \text{stpcst}$  for method **Nag\_RK\_4.5** or **Nag\_RK\_7.8** and  $3 \times \text{stpsok} \times \text{stpcst}$  for method = **Nag\_RK\_2.3**.

After a failure with `fail.code` = **NE\_RK\_PDC\_STEP**, **NE\_RK\_PDC\_GLOBAL\_ERROR\_T** or **NE\_RK\_PDC\_GLOBAL\_ERROR\_S** the diagnostic function `nag_ode_ivp_rk_errass` (d02pzc) may be called only once.

If `nag_ode_ivp_rk_onestep` returns with `fail.code` = **NE\_STIFF\_PROBLEM** then it is advisable to change to another code more suited to the solution of stiff problems. `nag_ode_ivp_rk_onestep` will not return with `fail.code` = **NE\_STIFF\_PROBLEM** if the problem is actually stiff but it is estimated that integration can be completed using less function evaluations than already computed.

**6.1. Accuracy**

The accuracy of integration is determined by the parameters **tol** and **thres** in a prior call to `nag_ode_ivp_rk_setup` (d02pvc). Note that only the local error at each step is controlled by these parameters. The error estimates obtained are not strict bounds but are usually reliable over one step. Over a number of steps the overall error may accumulate in various ways, depending on the properties of the differential system.

**6.2. References**

Brankin R W, Gladwell I and Shampine L F (1991) *RKSUITE: a suite of Runge-Kutta codes for the initial value problem for ODEs* SoftReport 91-S1, Department of Mathematics, Southern Methodist University, Dallas, TX 75275, U.S.A.

**7. See Also**

`nag_ode_ivp_rk_setup` (d02pvc)  
`nag_ode_ivp_rk_reset_tend` (d02pwc)  
`nag_ode_ivp_rk_interp` (d02pxc)  
`nag_ode_ivp_rk_errass` (d02pzc)

## 8. Example

We solve the equation

$$y'' = -y, \quad y(0) = 0, y'(0) = 1$$

reposed as

$$y_1' = y_2 \quad y_2' = -y_1$$

over the range  $[0, 2\pi]$  with initial conditions  $y_1 = 0.0$  and  $y_2 = 1.0$ . We use relative error control with threshold values of  $1.0e-8$  for each solution component and print the solution at each integration step across the range. We use a medium order Runge-Kutta method (**method** = **Nag\_RK\_4.5**) with tolerances **tol** =  $1.0e-4$  and **tol** =  $1.0e-5$  in turn so that we may compare the solutions. The value of  $\pi$  is obtained by using X01AAC.

See also the example programs for nag\_ode\_ivp\_rk\_reset\_tend (d02pwc) and nag\_ode\_ivp\_rk\_interp (d02pxc).

### 8.1. Program Text

```

/* nag_ode_ivp_rk_onestep(d02pdc) Example Program
 *
 * Copyright 1994 Numerical Algorithms Group.
 *
 * Mark 3, 1994.
 *
 */

#include <nag.h>
#include <math.h>
#include <stdio.h>
#include <nag_stdlib.h>
#include <nagd02.h>
#include <nagx01.h>

#ifdef NAG_PROTO
static void f(Integer neq, double t1, double y[], double yp[], Nag_User *comm);
#else
static void f();
#endif

#define NEQ 2
#define ZERO 0.0
#define ONE 1.0
#define TWO 2.0
#define FOUR 4.0

main()
{
    Integer neq;
    Nag_RK_method method;
    double hstart, pi, tnow, tend;
    double tol, tstart;
    Integer i;
    double thres[NEQ], ynow[NEQ], ypnw[NEQ], ystart[NEQ];
    Nag_ErrorAssess errass;
    Nag_ODE_RK opt;
    Nag_User comm;

    Vprintf("d02pdc Example Program Results\n");

    /* Set initial conditions and input for d02pvc */
    neq = NEQ;
    pi = X01AAC;
    tstart = ZERO;
    ystart[0] = ZERO;
    ystart[1] = ONE;
    tend = TWO*pi;

```

```

for (i=0; i<=neq; i++)
    thres[i] = 1.0e-8;
errass = Nag_ErrorAssess_off;
hstart = ZERO;
method = Nag_RK_4_5;

for (i=1; i<=2; i++)
{
    if (i==1) tol = 1.0e-4;
    if (i==2) tol = 1.0e-5;
    d02pvc(neq, tstart, ystart, tend, tol, thres, method,
          Nag_RK_onestep, errass, hstart, &opt, NAGERR_DEFAULT);

    Vprintf("\nCalculation with tol = %8.1e\n\n",tol);
    Vprintf("      t      y1      y2\n\n");
    Vprintf("%8.3f  %8.3f  %8.3f\n", tstart, ystart[0], ystart[1]);
    do
    {
        d02pdc(neq, f, &tnow, ynow, ynow, &opt, &comm,
              NAGERR_DEFAULT);
        Vprintf("%8.3f  %8.3f  %8.3f\n", tnow, ynow[0], ynow[1]);
    } while (tnow<tend);

    Vprintf("\nCost of the integration in evaluations of f is %ld\n\n",
          opt.totfcn);
    d02ppc(&opt);
}
exit(EXIT_SUCCESS);
}
#ifdef NAG_PROTO
static void f(Integer neq, double t, double y[], double yp[], Nag_User *comm)
#else
static void f(neq, t, y, yp, comm)
Integer neq;
double t;
double y[], yp[];
Nag_User *comm;
#endif

{
    yp[0] = y[1];
    yp[1] = -y[0];
}

```

## 8.2. Program Data

None.

## 8.3. Program Results

d02pdc Example Program Results

Calculation with tol = 1.0e-04

t	y1	y2
0.000	0.000	1.000
0.785	0.707	0.707
1.519	0.999	0.051
2.282	0.757	-0.653
2.911	0.229	-0.974
3.706	-0.535	-0.845
4.364	-0.940	-0.341
5.320	-0.821	0.571
5.802	-0.463	0.886
6.283	0.000	1.000

Cost of the integration in evaluations of f is 78

Calculation with tol = 1.0e-05

t	y1	y2
0.000	0.000	1.000
0.393	0.383	0.924
0.785	0.707	0.707
1.416	0.988	0.154
1.870	0.956	-0.294
2.204	0.806	-0.592
2.761	0.371	-0.929
3.230	-0.088	-0.996
3.587	-0.430	-0.903
4.022	-0.771	-0.637
4.641	-0.997	-0.072
5.152	-0.905	0.426
5.521	-0.690	0.724
5.902	-0.372	0.928
6.283	0.000	1.000

Cost of the integration in evaluations of f is 118

---